


Original Recipe by:
Ivan Castillo

HOMEBREW SUMMER

HOME BREW MART
INGRAINED SINCE 1992



FLIGHT TO CANCUN – MANGO BLONDE

BREW DAY

Stage/Time	Type	Qty	Name	%AA	IBU
Steep	Grain	1.75 lb	White Wheat Malt	-	-
		0.42 lb	Flaked Wheat	-	-
		0.25 lb	Honey Malt	-	-
Boil/15 min	Extract	5 lb	Golden Light DME	-	-
	Clarifier	1 tab	Whirlfloc	-	-
	Nutrient	1 tsp	Yeast Nutrient	-	-
Whirlpool	Hop	1 oz	Lupomax Krush	18%	11.2
		1 oz	Dolcita	10%	6.2



Blonde Ale (18A)

Original Gravity: 1.038 – 1.054 SG

Final Gravity: 1.008 – 1.013 SG

Bitterness: 15 – 28 IBUs

ABV: 3.8 – 5.5%

SRM: 3 - 6

Overall Impression: Easy-drinking, approachable, malt-oriented American craft beer, often with interesting fruit, hop, or character malt notes. Well-balanced and clean, is a refreshing pint without aggressive flavors.

FERMENTATION AND BEYOND

Stage	Type	Qty	Name	Notes
Pitch	Yeast	1 lg	SafAle US-05 American	68-72°F
High Krausen	Fruit	3 lb	Oregon Mango Puree	Add fruit and pectic enzyme together
	Enzyme	2tsp / 5drops	Pectic Enzyme	

TARGET STATS

Batch Size	5 gal
Original Gravity	1.049
Final Gravity	1.012
~%ABV	5.5
IBU	17
SRM	4.8

BREW NOTES

Boil Duration	60 min
Whirlpool Temp	194°F
Whirlpool Time	30 min

Notes

To maximize the efficiency of the puree, wait until the fermentation is at its peak (called “high krausen”). At this stage, yeast have reached their maximum population and are at their most active.

Please also be aware, this will increase the potential alcohol beyond the initial OG measurement. Without this addition, ABV will be approx. 5%

QUICK BREWING INSTRUCTIONS

PREP	Measure out all your ingredients ahead of time: - 3 gallons of water in your boil kettle - 3 gallons of sanitized, pre-chilled water in the fridge - All boil additions, ideally marked with their appropriate timings Pour pre-milled grain into a steeping bag and tie the top of the bag into a knot.		
STEEP	Not all recipes will call for steeping grains, since some beers benefit from being as dry in flavor and pale in color as possible. Steeping grains are used to increase the color, the sweetness, and the overall density of your finished beer. Think of it like making a very large cup of malt tea, except you don't want to use boiling water. Your ideal temperature range for the steep is between 150 and 155°F. 1. Heat your water up to 158°F, then turn off your heat and add your steeping bag of grain. This should bring the temperature down to 155°F or so. The larger your bag of steeping grains, the more it will change the temperature of the water. 2. Cover the pot with a lid to maintain temperature for 30 minutes. After 30 minutes, remove the grain from the pot and let it drip over the pot for a few moments before discarding. Do not squeeze or wring out the bag.		
BOIL	The purpose of your boil is to: [1] to sanitize, [2] to extract bitterness (alpha acids) from hops, and [3] to break down particulates for a clearer finished product. The total boil time is largely determined by how bitter you intend the beer to be. The extract only needs to be boiled long enough to sanitize and break down particulates, which is why our recipes usually add extracts in the last 15 minutes of the boil. 1. Once your steep is complete and the grain bag is removed, begin heating your pot to a boil. 2. Once you achieve a stable rolling boil, start your timer for the total boil time (see recipe) and begin adding your additions at the appropriate times. With each addition, be sure to add slowly and keep an eye out for boil-overs. 3. In between additions, you should take the opportunity to make a bucket for sanitizing any equipment that will contact your unfermented beer (called "wort") after the boil. a. Measure out 5 gallons of water in your fermentor and add 1 oz of sanitizer. If you haven't already, be sure to mark your fermentor at the 5 gallon level for later. b. After about a minute, transfer the solution into a bucket to sanitize the rest of your equipment (e.g. funnel, airlock, stopper, wine thief, etc.) Note: If it's a glass fermentor, do not pick it up and attempt to pour it out; use a siphon to transfer the liquid safely. 4. With 15 min left of the boil, turn off the heat to the pot. Slowly add your malt extract, constantly stirring to ensure that it is completely dissolved. When clumps are no longer visible, turn the heat back on to resume boiling. At this point, boil-overs are much more likely, so have countermeasures ready. When the foam begins to rise rapidly: a. Be prepared to turn the heat down or off. b. Have a spray bottle of water ready to help keep the foam at bay. c. If the foam does not re-incorporate into the wort on its own, the heat is too high. 5. Add any further additions at the appropriate times and begin preparing your cooldown bath.	60 MIN	
		15 MIN	• 5lb Light DME • Clarifier & Nutrient
		WHIRLPOOL	Add @ 194°F, steep for 30 min • 1 oz Lupomax Krush • 1 oz Dolcita
COOLDOWN	Now that your boil has concluded, everything that touches your wort must be sanitized. Cooling your wort down to pitchable temperatures is important to improve clarity and to reduce the chances of bacterial infection. 1. Transfer the hot kettle from the burner to a sink or tub filled with cold water. Carefully swirl the pot to better cool the wort inside. Note: Do not add ice at this time. Cold tap water should be enough of a contrast to rapidly cool your near-boiling wort to more manageable temperatures. Save the ice for the hard part (i.e. getting from 120°F to 80°F or lower). 2. As the water becomes hot, refill your tub with cool water until the wort gets below 150°F. At this point adding ice to the bath can help cool the wort to target more quickly. 3. Once your wort has cooled to 80°F or less, vigorously pour it into your sanitized fermentor. Add the prepared, sanitized cold water (refrigerating the water as suggested in the prep stage will help to cool your wort even further) to the fermentor until the total volume has reached 5 gallons. Shake the carboy for a few minutes to oxygenate and to evenly mix the water with your wort. Now is the time to take a hydrometer reading and record your Original Gravity measurement.		
PITCH	Adding your yeast is what changes the liquid in your fermentor from "wort" to "beer." 1. Sanitize the exterior of the yeast package as well as any tools used to open it. 2. Add your yeast to the fermentor and seal with an airlock and stopper—being sure to fill the airlock to the appropriate mark with sanitizing solution. 3. Store in a cool dark place for the duration of fermentation.	SafAle US-05 – American Ale Yeast <i>Ferment at 68 – 72F</i>	
KRAUSEN	To maximize flavor retention and ensure all sugars are fermented out, fruit additions are often added at the peak of fermentation "high krausen". When a thick layer of foam appears on the top of your beer and your airlock is bubbling merrily, remove your airlock and add these fruit additions. Remember that your beer is still vulnerable to infection, so be sure to add only sanitized ingredients at this stage. 1. Alternatively, if you are kegging instead of bottle conditioning, you have the option to add the mango puree after fermentation is already completed. This will preserve more of the mango flavor and a lot of the sugar. For anyone carbonating naturally in the bottle, we recommend adding the puree at high krausen so all sugars are converted during fermentation and priming can be completed as usual.	• 3 lb Mango Puree • 2 tsp / 5 drops Pectic Enzyme	