

Original Recipe by:
Paul Brown

Homebrew Summer

HOME BREW MART
INGRAINED SINCE 1992



TIME MOVING SLOW – WEST COAST PILSNER

BREW DAY

Stage/Time	Type	Qty	Name	%AA	%/IBU
Mash Target pH: 5.3	Grain	5.75 lb	Idaho Pilsner	-	65.7%
		2.5 lb	Golden Promise	-	28.6%
		0.5 lb	Chit Malt	-	5.7%
Boil/60min	Hop	1 oz	Hallertaur	3.4%	12.4
Boil/10min	Hop	1.5 oz	Citra	12.2%	24.1
	Fining	1 tablet	Whirlfloc	-	-
	Nutrient	½ tsp	Yeast nutrient	-	-
Whirlpool	Hop	1.5 oz	Citra	12.2%	11
		1.5 oz	Mosaic	13.4%	12.1
		1 oz	Krush	13.3%	8



Mixed Style Beer (34B)

Original Gravity: 1.020 – 1.090 SG

Final Gravity: 1.006 – 1.016 SG

Bitterness: 40 – 70 IBUs

ABV: 2 – 10%

SRM: 2 - 50

Overall Impression: This beer is a combination of IPA and Pilsner. It doesn't quite fit either the India Pale Lager or New Zealand Pilsner due to it's lower ABV, relatively high bitterness, and inclusion of West Coast hops Expect it to be refreshingly dry, bracingly bitter, with a dramatic dry-hop.

FERMENTATION AND BEYOND

Stage	Type	Qty	Name	Notes
Pitch	Yeast	1 lg	LalBrew NovaLager	59-68°F
Dry Hop	Hop	1 oz	Cryo Citra	3 days ⇒ bottle
		1 oz	Cryo Krush	
		1 oz	Cryo Mosaic	

TARGET STATS

Batch Size	5 gal
OG	1.044
FG	1.006
~%ABV	5.0
%Efficiency	72
IBU	67
SRM	3

BREW NOTES

Mash Temp	149°F
Mash Duration	60 min
Boil Volume	6.5 gal
Boil Duration	60 min
Whirlpool Temp	180°F
Whirlpool Time	20 min

Notes

Whirlpool duration and temperature can make a difference with the final bitterness of a beer. With this recipe, allow the wort to cool down to 180°F, add your hops and steep for 20 minutes, before cooling to pitch temperature.

Pitch yeast and ferment at 55°F. Once gravity dips below 1.020, bring temperature up to 58°F again for a diacetyl rest.

QUICK BREWING INSTRUCTIONS

MASH	Mashing is the process of soaking milled, malted barley in hot water to convert starch into fermentable sugars. The success of this process is measured as percent efficiency and is reliant on maintaining the appropriate temperature and water to grain ratio of 1.25 quarts per pound of grain. 1. Measure out your water for mash and heat to your strike temperature. 2. Slowly add your grain, constantly stirring to break up dough balls and consistent mixture. 3. Check that your temperature is on target and seal your mash tun. 4. If your equipment has a recirculation pump, now is the time to run it. 5. While you wait for the mash to finish, begin heating your water for the sparge.	<table><tr><th colspan="2">Mash Targets</th></tr><tr><td>Mash Water</td><td>3.6 gal</td></tr><tr><td>Strike Temp</td><td>160°F</td></tr><tr><td>Mash Temp</td><td>149°F</td></tr><tr><td>Duration</td><td>60 min</td></tr></table>	Mash Targets		Mash Water	3.6 gal	Strike Temp	160°F	Mash Temp	149°F	Duration	60 min				
Mash Targets																
Mash Water	3.6 gal															
Strike Temp	160°F															
Mash Temp	149°F															
Duration	60 min															
LAUTER & SPARGE	Once the starch conversion is complete, the liquid (“sweet wort”) needs to be separated (“lautered”) from the grain which then needs to be rinsed (“sparged”) to extract as much sugar as possible. 1. Measure out your sparge water and heat to 168°F. 2. Position your kettle below your mash tun and your sparge tank above. 3. If your brewing equipment did not include a recirculation pump for the mash, you’ll need to do this manually. a. Partially open the valve on the mash tun and use 2 pitchers or large measuring cups to catch the stream that begins to flow; you’ll notice a lot of small particles floating in the wort. As each pitcher fills, replace it with an empty one and pour the full pitcher gently back into the mash tun. Continue doing this until your wort is relatively free of particles. 4. With sparge tank and kettle in place, mash complete, and grain bed set, it’s time to start lautering into the kettle. As wort drains from the mash, sparge water should replace it at the same rate from above, ideally maintaining an inch or so of water above the surface of the grain. Adjust your flow rates at the sparge tank or mash tun accordingly. 5. Once the target boil volume is reached in the kettle you can turn off valves and stop the flow into the kettle. Start heating up to a boil.	<table><tr><th colspan="2">Sparge Targets</th></tr><tr><td>Volume</td><td>5 gal</td></tr><tr><td>Temp</td><td>168°F</td></tr></table> <table><tr><th colspan="2">Boil Targets</th></tr><tr><td>Volume</td><td>6.5 gal</td></tr><tr><td>Duration</td><td>60 min</td></tr><tr><td>Pre-Boil SG</td><td>1.039</td></tr></table> Note: The mash water calculated above assumes no deadspace below the grain. If you are using an all-in-one system and your mash seems especially thick, you may need to add more water to compensate.	Sparge Targets		Volume	5 gal	Temp	168°F	Boil Targets		Volume	6.5 gal	Duration	60 min	Pre-Boil SG	1.039
Sparge Targets																
Volume	5 gal															
Temp	168°F															
Boil Targets																
Volume	6.5 gal															
Duration	60 min															
Pre-Boil SG	1.039															
BOIL & COOLDOWN	The purpose of your boil is 1) to sanitize, 2) to extract bitterness (alpha acids) from hops, and 3) to break down particulates for a clearer finished product. 1. As your wort nears the boil, be prepared to turn down the heat or add foam control to prevent boil-overs. 2. Once you reach a steady rolling boil, add your first boil addition and start your timer counting down to the next addition (i.e. if it’s a 60 min boil and your next addition is at the 15 min mark, start your timer for 45 minutes). Add all other additions at their appropriate times. 3. Sanitize all other equipment that will contact your wort after the boil. 4. If you’re using an immersion chiller, attach tubes and submerge in pot at the 15 min mark to sanitize. 5. Once your full boil time has elapsed, it’s time to start the cooldown. Start running water through your immersion chiller. The outgoing water will be steaming hot, so be sure the outflow is directed somewhere safe. 6. If the spigot on your kettle draws from the side, you can benefit from a whirlpool step: a. Remove your wort chiller and use a sanitized metal spoon to rapidly stir your cooled wort to create a whirlpool. The hop sediment and other hot break material will be sucked to the center of the pot. If you then allow it to settle undisturbed for 10-15 minutes, that sediment will sink to the bottom in a more easily avoidable area. You can then rack (transfer) the clear wort from the spigot or using a racking cane, leaving that sediment behind. 7. Once cooled to fermentation temperature, whirlpooled, and allowed to settle, it’s time to rack into your sanitized fermentor.	<table><tr><td>60MIN</td><td> • 1 oz Citra </td></tr><tr><td>10 MIN</td><td> • 1.5 oz Citra • Clarifier & Nutrient </td></tr><tr><td>WHIRLPOOL</td><td> Add at 180°F and steep for 20 min • 1.5 oz Citra • 1.5 oz Mosaic • 1 oz Krush </td></tr></table>	60MIN	• 1 oz Citra	10 MIN	• 1.5 oz Citra • Clarifier & Nutrient	WHIRLPOOL	Add at 180°F and steep for 20 min • 1.5 oz Citra • 1.5 oz Mosaic • 1 oz Krush								
60MIN	• 1 oz Citra															
10 MIN	• 1.5 oz Citra • Clarifier & Nutrient															
WHIRLPOOL	Add at 180°F and steep for 20 min • 1.5 oz Citra • 1.5 oz Mosaic • 1 oz Krush															
PITCH	Adding your yeast is what changes the liquid in your fermentor from “wort” to “beer.” 1. Sanitize the exterior of the yeast package as well as any tools used to open it. 2. Add your yeast to the fermentor and seal with an airlock and stopper—being sure to fill the airlock to the appropriate mark with sanitizing solution. 3. Store in a cool dark place for the duration of fermentation.	LalBrew NovaLager Ferment at 55 – 58°F														
DRY HOP	The dry hop stage comes after fermentation is complete. Unlike hops adding during the boil, dry hop additions contribute only hoppy aroma—not bitterness—to the finished beer. To maximize flavor retention, wait until fermentation activity (i.e. bubbling in the airlock) has ceased. 1. Remove your airlock and pour your dry hop additions directly into the beer. Replace airlock..	• 1 oz Cryo Citra • 1 oz Cryo Mosaic • 1 oz Cryo Krush Package after 3 more days														